


USER'S MANUAL

ILDA Viewer




Content

1 Introduction.....	3
2 Open Files	3
3 Views.....	4
4 Frame Selection.....	7
5 Keyboard Shortcuts.....	8



1 Introduction

The ILDA Viewer is used to display files in "ILDA Image Data Transfer Format". In addition you can also get detailed information about the displayed file.




2 Open Files

The file can be opened as follows:

- Menu option "File" -> "Open..."
- Keyboard shortcut <Ctrl>+<O>
- Drag&Drop the file into the main window
- Double click on file


3 Views

There are four different views:




- Front:**
- Menu option "View" -> "Front"
 - Keyboard shortcut <Ctrl>+<F>
 - Click the view "Front"
- Side:**
- Menu option "View" -> "Side"
 - Keyboard shortcut <Ctrl>+<S>
 - Click the view "Side"
- Top:**
- Menu option "View" -> "Top"
 - Keyboard shortcut <Ctrl>+<T>
 - Click the view "Top"
- Perspective:**
- Menu option "View" -> "Perspective"
 - Keyboard shortcut <Ctrl>+<P>
 - Click the view "Perspective"

You can display a single view



or all four views simultaneously:

- Menu option "View" -> "All"
- Keyboard shortcut <Ctrl>+<A>



Zoom and Panning in the Views "Front" / "Side" / "Top":

Zoom:

- Menu option "View" -> "Zoom In" / "Zoom Out"
- Keyboard shortcut <Ctrl>+<+> / <Ctrl>+<->
- Mouse wheel while holding down <Ctrl>

Panning:

- Move mouse while holding down the mouse button
Fine Mode: Middle mouse button or left mouse button while holding down
- Keyboard: Cursor keys

Reset Zoom and Panning:

- Menu option "View" -> "Reset"
- Keyboard shortcut <Ctrl>+<0>
- Double-click the view

Zoom and Rotation in the View "Perspective":

Zoom:

- Menu option "View" -> "Zoom In" / "Zoom Out"
- Keyboard shortcut <Ctrl>+<+> / <Ctrl>+<->
- Mouse wheel while holding down <Ctrl>

Rotation:

- Move mouse while holding down the mouse button
Fine Mode: Middle mouse button or left mouse button while holding down <Alt>
- Keyboard: Cursor keys

Reset Zoom and Rotation:

- Menu option "View" -> "Reset"
- Keyboard shortcut <Ctrl>+<0>
- Double-click the view

4 Frame Selection

If the file contains multiple frames, you can select the frame as follows:

- Menu option "Frame" -> "First" / "Previous" / "Next" / "Last"
- Keyboard shortcut <Ctrl>+<Home> / <PgUp> / <PgDown> / <Ctrl>+<End>
- Keyboard shortcut <+> / <->
- Scrollbar at the bottom of the main window
- Mouse wheel

5 Keyboard Shortcuts

Function	Shortcut	Menu
Open file	<Ctrl>+<O>	"File" -> "Open..."
Exit	<Ctrl>+<Q>	"File" -> "Exit"
Zoom in	<Ctrl>+<+>	"View" -> "Zoom In"
Zoom out	<Ctrl>+<->	"View" -> "Zoom Out"
Reset zoom and panning/rotation	<Ctrl>+<0>	"View" -> "Reset"
Activate view "Front"	<Ctrl>+<F>	"View" -> "Front"
Activate view "Side"	<Ctrl>+<S>	"View" -> "Side"
Activate view "Top"	<Ctrl>+<T>	"View" -> "Top"
Activate view "Perspective"	<Ctrl>+<P>	"View" -> "Perspective"
Toggle between four views and single view	<Ctrl>+<A>	"View" -> "All"
Select first frame	<Ctrl>+<Home>	"Frame" -> "First"
Select previous frame	<PgUp> or <->	"Frame" -> "Previous"
Select next frame	<PgDown> or <+>	"Frame" -> "Next"
Select last frame	<Ctrl>+<End>	"Frame" -> "Last"
Enable/disable display of blanked lines	<Ctrl>+	"Options" -> "Show Blanked Lines"
Enable/disable display of dots	<Ctrl>+<D>	"Options" -> "Show Dots"
Open/close window "Information"		"Options" -> "Show Information"
Display program version and copyright	<Ctrl>+<I>	"Help" -> "About"
Toggle between window and full screen mode	<Alt>+<Return>	