



Quick Start Guide

1

Download and install **proTize converter** (Standalone version) from the [download area](#) of LaserAnimation website. If you want to convert SVG files you also have to download and install **Inkscape**. Once installed, launch proTize converter and enter your license key to activate it. *An internet connection is required for activation.

2

For your first conversion, you will use the sample turtle animation. If you did not change the default installation path, the samples and manual can be found in “C:\Program Files\proTize converter”. **Drag and drop** the entire turtle folder into the **Input Preview window** on the left. The conversion result will appear in the **Final Preview window** on the right, and the process should complete within a few seconds.

3

To export **ILDA files** to a specific location, go to the main menu and open **Properties → Row Properties**. Specify your desired save path in Destination, and then check the box for **Write ILDA format** to enable it. Drag and drop the turtle folder into the Input Preview window once more, and the turtle ILDA file will be generated in your designated folder.



The scanner-simulated **Super Preview** can be opened from Window in the proTize converter menu.

The comprehensive proTize converter **manual** is highly useful for looking up parameter details.

Additional sample files are available for download on the LaserAnimation website. Feel free to explore and try out the **various samples!**

The windows of the proTize converter

